

# Restore machine calibration

---



You can download and restore the results of previous machine calibrations performed by the target retrofit.

Available in V1.0.04 or later.

## **Important**

After restoring the calibration file, be sure to check the following

- > The reflected calibration is correct.
- > The bucket cutting edge position is correct.

# 01

## Chapter

---

### How to use


---

# 1.1 Flow of Use

To restore machine calibration, access the following.



Menu → Administrator Settings → Machine Calibration Settings → Restore Machine Calibration

The usage flow is as follows.




## 1.2 Getting a Calibration File


Download the calibration file. The date is the date and time the calibration was registered on the server.

1. Acquired calibration files are listed.
2. Tap the  button
3. Calibration files on the server are listed.
4. Tap the  button to download the selected calibration file.




# 1.3 Selecting the acquired calibration file


1. Calibration files that have been saved in the app (target retrofit) are listed
2. Tap the  of the file you want to restore

※ Tap  to load the calibration file from the tablet (SD card or storage). In this case, the date and time when the file was loaded will be displayed.


When replacing the controller, if you save the calibration file used before the replacement in the tablet's download folder and then use this function to load it, you can restore the settings.





# 1.4 Confirmation and Application of Restore

1. Confirmation screen of machine calibration restoration contents appears.
2. Tap  button
3. Notification screen (update confirmation screen) appears

 → Cancel       → Update settings

※ Tap  on the application confirmation screen to delete the calibration file loaded in the application.



# Contact information

---



## **Inquiries about products and defects:**

EARTH BRAIN Co., Ltd.

Support site inquiries :

[Europe](#)

[US](#)

[Australia](#)

[Asia](#)